# MCW AFNI — Buckets Robert W. Cox, Ph.D.

rwcox@mcw.edu

© 1997 Medical College of Wisconsin

# The New 'Bucket' Dataset Type

A bucket dataset is a 3D dataset that can contain an arbitrary number of sub-bricks. These sub-bricks are not considered to be time-ordered; rather, the bucket dataset type is a place where the user can toss 3D bricks of data.

This documentation is provided to update the AFNI plugins manual and to explain the programmatic interface for creating bucket datasets. It is current as of AFNI 2.20, and is at present a work-in-progress (i.e., subject to change at a moment's whim).

Note that the entire MCW AFNI package—including plugins—must be recompiled to use these features. This is because the internal storage scheme used for datasets has been modified slightly.

### Contents

1	Sub-brick Auxiliary Data	2
2	Program 3dbucket	3
3	Program 3drefit	5
4	Creating Buckets in a Program	7
5	Changes in AFNI	15
6	Still to Come	15

It has always been possible to create a 3D (no time) dataset with multiple sub-bricks. Until now, there has not been any program that would do this, nor would any but the first sub-brick be visible from within AFNI. The new program 3dbucket allows the creation of datasets with an arbitrary number of sub-bricks drawn from the bricks of existing dataset. AFNI has been modified to allow the user to switch viewing between sub-bricks. The dataset structure has been extended to allow extra information to be attached to each sub-brick to make them easy to distinguish. A programming interface has been implemented that allows external programs (and plugins) to create 3D bucket datasets.

## 1 Sub-brick Auxiliary Data

Three new types of data can be associated with each sub-brick in any AFNI dataset (bucket,  $3D+time, \ldots$ ). They are

**Label** This is a character string that is displayed on the AFNI bucket chooser menu that lets the user decide which sub-brick should be displayed (see §5).

**Keywords** This is a character string that contains a list of keywords that are to be associated with a given sub-brick. Each keyword is separated by the C substring "; ". At present, the keywords have no function within any MCW *AFNI* program, but that is likely to change shortly.

Statistical Parameters Each sub-brick can have a statistical type attached, exactly as some of the earlier function types can. If a sub-brick with a valid statistical type is chosen to be the threshold sub-brick from within AFNI, then the nominal p-value per voxel will be displayed beneath the threshold slider.

Most of these sub-brick statistical types require auxiliary parameters. The list of statistical types is:

Name	Type Code	Distribution	Auxiliary parameters
fico	FUNC_COR_TYPE	Correlation Coeff	# Samples, # Fit Param, # Ort Param
fitt	FUNC_TT_TYPE	Student t	Degrees-of-Freedom (DOF)
fift	FUNC_FT_TYPE	F ratio	Numerator DOF, Denominator DOF
fizt	FUNC_ZT_TYPE	Standard Normal	— none —
fict	FUNC_CT_TYPE	Chi-Squared	DOF
fibt	FUNC_BT_TYPE	Incomplete Beta	Parameters $a$ and $b$
fibn	FUNC_BN_TYPE	Binomial	# Trials, Probability per trial
figt	FUNC_GT_TYPE	Gamma	Shape, Scale
fipt	fipt   FUNC_PT_TYPE   Poisson		Mean

The 'Name' is used on the command line when modifying the auxiliary data inside a dataset using the program 3drefit. The 'Type Code' is a C macro for a constant that is used from within a program when modifying the auxiliary data.

In addition to the sub-brick specific keywords list, I have also added a global keywords list that pertains to the entire dataset. One ultimate purpose of the keywords lists is to allow the selection of datasets and sub-bricks based on keywords.

It is possible to attach a label and a statistical type to sub-bricks of non-bucket datasets. But they will have no effect.

# 2 Program 3dbucket

At this moment, the only program that can create a bucket dataset is 3dbucket. (In particular, to3d cannot create a bucket dataset!) 3dbucket concatenates 3D sub-bricks from multiple input datasets and produce one output bucket dataset. The main purpose of this program is to experiment with bucket datasets. Its help file follows:

```
Usage: 3dbucket options
where the options are:
     -prefix pname = Use 'pname' for the output dataset prefix name.
                       [default='buck']
 OR -output pname
     -session dir = Use 'dir' for the output dataset session directory.
                       [default='./'=current working directory]
     -dry
                   = Execute a 'dry run'; that is, only print out
                       what would be done. This is useful when
                       combining sub-bricks from multiple inputs.
                   = Print out some verbose output as the program
     -verb
                       proceeds (-dry implies -verb).
     -fbuc
                   = Create a functional bucket.
                   = Create an anatomical bucket. If neither of
     -abuc
                       these options is given, the output type is
                       determined from the first input type.
```

Other arguments are taken as input datasets. A dataset is specified using one of the forms

'prefix+view', 'prefix+view.HEAD', or 'prefix+view.BRIK'.
You can also add a sub-brick selection list after the end of the dataset name. This allows only a subset of the sub-bricks to be included into the output (by default, all of the input dataset is copied into the output). A sub-brick selection list looks like one of the following forms:

```
fred+orig[5] ==> use only sub-brick #5
fred+orig[5,9,17] ==> use #5, #9, and #12
fred+orig[5..8] or [5-8] ==> use #5, #6, #7, and #8
fred+orig[5..13(2)] or [5-13(2)] ==> use #5, #7, #9, #11, and #13
Sub-brick indexes start at 0. You can use the character '$'
```

to indicate the last sub-brick in a dataset; for example, you can select every third sub-brick by using the selection list fred+orig[0..\$(3)]

- N.B.: The sub-bricks are output in the order specified, which may not be the order in the original datasets. For example, using fred+orig[0..\$(2),1..\$(2)] will cause the sub-bricks in fred+orig to be output into the new dataset in an interleaved fashion. Using fred+orig[\$..0]
- will reverse the order of the sub-bricks in the output.
- N.B.: Bucket datasets have multiple sub-bricks, but do NOT have a time dimension. You can input sub-bricks from a 3D+time dataset into a bucket dataset. You can use the '3dinfo' program to see how many sub-bricks a 3D+time or a bucket dataset contains.
- N.B.: The '\$', '(', ')', '[', and ']' characters are special to the shell, so you will have to escape them. This is most easily done by putting the entire dataset plus selection list inside single quotes, as in 'fred+orig[5..7,9]'.

#### Some additional points:

- If an input sub-brick has a statistical type, then its type and auxiliary parameters are copied to the output sub-brick. This happen if the input dataset is one of the functional types with a statistics threshold attached (e.g., the second sub-brick from a fico dataset). It can also happen if the input dataset is itself a bucket dataset.
- The sub-brick labels for the output dataset are of the form prefix[index], where 'prefix' is the input dataset and 'index' is the integer index of the sub-brick in the input dataset.
- The output sub-brick keywords are copied from the input sub-bricks, if any. The additional keyword prefix+view[index] is also attached to the sub-brick keyword list.
- I intend to extend the input sub-brick selection scheme for 3dbucket to allow selection from keyword lists. Eventually, it will also be possible to construct datasets 'on-the-fly' on the command line for any program.
- Anatomical bucket datasets are not particularly useful, at least at present. (Got any ideas for applications?)

## 3 Program 3drefit

This program lets the user change the contents of a dataset header. It has been extended to let the sub-brick auxiliary data be modified. Its help file follows:

Usage: 3drefit [options] dataset ... where the options are -orient code Sets the orientation of the 3D volume(s) in the .BRIK. The code must be 3 letters, one each from the pairs {R,L} {A,P} {I,S}. The first letter gives the orientation of the x-axis, the second the orientation of the y-axis, the third the z-axis: L = left-to-right R = right-to-left A = anterior-to-posterior P = posterior-to-anterior I = inferior-to-superior S = superior-to-inferior \*\* WARNING: when changing the orientation, you must be sure to check the origins as well, to make sure that the volume is positioned correctly in space. -xorigin distx Puts the center of the edge voxel off at the given -yorigin disty distance, for the given axis (x,y,z); distances in mm. -zorigin distz (x=first axis, y=second axis, z=third axis). Usually, only -zorigin makes sense. Note that this distance is in the direction given by the corresponding letter in the -orient code. For example, '-orient RAI' would mean that '-zorigin 30' sets the center of the first slice at 30 mm Inferior. See the to3d manual for more explanations of axes origins. \*\* SPECIAL CASE: you can use the string 'cen' in place of a distance to force that axis to be re-centered. -xdel dimx Makes the size of the voxel the given dimension, -ydel dimy for the given axis (x,y,z); dimensions in mm. -zdel dimz \*\* WARNING: if you change a voxel dimension, you will probably have to change the origin as well. -TR time Changes the TR time to a new value (see 'to3d -help'). \*\* WARNING: this only applies to 3D+time datasets. -newid Changes the ID code of this dataset as well.

MCW AFNI Buckets -5- January 8, 1998

dataset. See 'to3d -help' for more details.

-statpar v ... Changes the statistical parameters stored in this

```
-markers
                Adds an empty set of AC-PC markers to the dataset,
                if it can handle them (is anatomical, doesn't already
                have markers, is in the +orig view, and isn't 3D+time).
-appkey ll
                Appends the string 'll' to the keyword list for the
                whole dataset.
-repkey 11
                Replaces the keyword list for the dataset with the
                string 'll'.
-empkey
                Destroys the keyword list for the dataset.
-type
                Changes the type of data that is declared for this
                dataset, where 'type' is chosen from the following:
     ANATOMICAL TYPES
       spgr == Spoiled GRASS
                                         fse == Fast Spin Echo
       epan == Echo Planar
                                        anat == MRI Anatomy
         ct == CT Scan
                                       spct == SPECT Anatomy
       pet == PET Anatomy
                                        mra == MR Angiography
       bmap == B-field Map
                                       diff == Diffusion Map
       omri == Other MRI
                                        abuc == Anat Bucket
     FUNCTIONAL TYPES
                                       fith == Inten+Thr
       fim == Intensity
       fico == Inten+Cor
                                       fitt == Inten+Ttest
                                      fizt == Inten+Ztest
fibt == Inten+Beta
       fift == Inten+Ftest
       fict == Inten+ChiSq
       fibn == Inten+Binom
                                       figt == Inten+Gamma
                                       fbuc == Func-Bucket
       fipt == Inten+Poisson
```

The options below allow you to attach auxiliary data to sub-bricks in the dataset. Each option may be used more than once so that multiple sub-bricks can be modified in a single run of 3drefit.

```
-sublabel n ll Attach to sub-brick #n the label string 'll'.
-subappkey n ll Add to sub-brick #n the keyword string 'll'.
-subrepkey n ll Replace sub-brick #n's keyword string with 'll'.
-subempkey n Empty out sub-brick #n' keyword string
-substatpar n type v ...
```

Attach to sub-brick #n the statistical type and the auxiliary parameters given by values 'v ...', where 'type' is one of the following:

type	Description	PARAMETERS
fico	Cor	SAMPLES FIT-PARAMETERS ORT-PARAMETERS
fitt	Ttest	DEGREES-of-FREEDOM
fift	Ftest	NUMERATOR and DENOMINATOR DEGREES-of-FREEDOM
fizt	Ztest	N/A
fict	ChiSq	DEGREES-of-FREEDOM
fibt	Beta	A (numerator) and B (denominator)
fibn	Binom	NUMBER-of-TRIALS and PROBABILITY-per-TRIAL
figt	Gamma	SHAPE and SCALE
fipt	Poisson	MEAN

3drefit is the only program that lets the user change the sub-brick label, keywords, and statistical parameters. In particular, if you don't like the default labels provided by 3dbucket, you must use 3drefit to patch things up. Program 3dinfo has been modified so that it will print out the sub-brick auxiliary data (including keywords). This will help guide the use of 3drefit.

# 4 Creating Buckets in a Program

#### Modifying Sub-Brick Parameters

Control Code

A number of new ADN\_ commands have been added to EDIT\_dset\_items in order to make creating bucket datasets moderately painless. In combination with a couple of other utility routines, it is possible to create an empty dataset with n sub-bricks, attach data arrays to them and auxiliary data to them, and even later to expand the number of sub-bricks.

The new ADN\_commands are described below. (This section should be read in conjunction with §2.7 of the AFNI plugins manual.) The inputs to EDIT\_dset\_items are copied into the internal data structure of the dataset being modified, and so can be freed or otherwise recycled after this function return. Bucket construction examples will be given later.

ADN_brick_label_one	char *	Unlike the earlier ADN_ codes, this one, and the
		others below that end in '_one' are be used to
		set auxiliary parameters for individual sub-bricks
		in a dataset. This is done by adding the sub-
		brick index to the ADN_ code. Note that only one
		version of any particular '_one' code can be used

Data Type Meaning

per call to EDIT\_dset\_items—to set multiple subbricks, a loop is required. This particular code is used to set the label that is displayed in the menu that is used to select which sub-brick is displayed.

ADN\_brick\_fac\_one float

This code is used to set the scale factor for an individual sub-brick. The alternative code, ADN\_brick\_fac (described in the plugins manual), is used to set *all* the sub-brick factors at once.

ADN\_brick\_stataux\_one

float \*

This code is used to set the auxiliary statistical parameters for an individual sub-brick. The float array that is passed as the paired argument must have the following contents:

statcode npar v1 v2 ... vn

where statcode is the type of statistic stored in the sub-brick, npar is the number of parameters that follow in the array, and v1... vn are the parameters for that type of statistic. (Note that npar may be 0.) See  $\S 1$  for details on the different statistical types supported by AFNI.

ADN\_brick\_keywords\_replace\_one

char \*

This code is used to delete the keywords associated with a sub-brick and replace them with a new set. The list of keywords is stored as a single string, with distinct entries separated by the substring ";". If you want to enter multiple distinct keywords with this operation, you must supply the "; "yourself within the paired argument.

ADN\_brick\_keywords\_append\_one

char \*

This code is used to add keywords to the list associated with a sub-brick. The input character string will be appended to the existing keyword string, with "; " separating them. (This function will supply the "; " separator.) If there are no keywords, this operation is equivalent to the replace function above.

ADN\_keywords\_replace char \*

This is used to replace the keywords list associated with the entire dataset.

ADN\_keywords\_append char \*

This is used to append to the keyword list for the entire dataset.

To make some of these steps easier, the following C macros have been defined:

- EDIT\_BRICK\_LABEL(ds,iv,str) will change the label in the iv<sup>th</sup> sub-brick of dataset ds to the string str.
- EDIT\_BRICK\_FACTOR(ds,iv,fac) will change the scaling factor in the iv<sup>th</sup> sub-brick of dataset ds to the float value fac.
- EDIT\_BRICK\_ADDKEY(ds,iv,str) will add the keyword string str to the iv<sup>th</sup> sub-brick of dataset ds.

- EDIT\_BRICK\_TO\_FICO(ds,iv,nsam,nfit,nort) changes the iv<sup>th</sup> sub-brick of dataset ds to be fico type (correlation coefficient) with statistical parameters nsam, nfit, and nort.
- EDIT\_BRICK\_TO\_FITT(ds,iv,ndof) changes the iv<sup>th</sup> sub-brick of dataset ds to be fitt (t-test) type with statistical parameter ndof.
- EDIT\_BRICK\_TO\_FIFT(ds,iv,ndof,ddof) changes the iv<sup>th</sup> sub-brick of dataset ds to be fift (F-test) type with statistical parameters ndof and ddof.
- EDIT\_BRICK\_TO\_FIZT(ds,iv) changes the iv<sup>th</sup> sub-brick of dataset ds to be fizt type (z-score, or normally distributed).
- EDIT\_BRICK\_TO\_FICT (ds,iv,ndof) changes the iv<sup>th</sup> sub-brick of dataset ds to be first type ( $\chi^2$  distributed) with statistical parameter ndof.
- EDIT\_BRICK\_TO\_FIBT(ds,iv,a,b) changes the iv<sup>th</sup> sub-brick of dataset ds to be fibt type (beta distributed) with statistical parameters a and b.
- EDIT\_BRICK\_TO\_FIBN(ds,iv,ntrial,prob) changes the iv<sup>th</sup> sub-brick of dataset ds to be fibn type (binomial distributed) with statistical parameters ntrial and prob.
- EDIT\_BRICK\_TO\_FIGT (ds,iv,shape,scale) changes the iv<sup>th</sup> sub-brick of dataset ds to be fign type (gamma distributed) with statistical parameters shape and scale.
- EDIT\_BRICK\_TO\_FIPT(ds,iv,mean) changes the iv<sup>th</sup> sub-brick of dataset ds to be fipt type (Poisson distributed) with statistical parameter mean.

#### Example: Creating a Bucket Dataset All at Once

In this example, an empty copy of an input dataset is made (to get the geometry correct), then the new dataset is turned into a function bucket, then the sub-bricks are attached. The following code is adapted from 3dbucket.c.

```
THD_3dim_dataset * old_dset , * new_dset ;
char * output_prefix , output_session ;
int new_nvals , iv ;
                      /* bar[iv] points to data for sub-brick #iv */
short ** bar ;
*/
                    /* new_fac[iv] is new scale factor for #iv
float * new_fac ;
                                                               */
float sax[32]; /* statistical auxiliary parameters
                                                               */
/*-- Copy the input dataset structure, but not data --*/
new_dset = EDIT_empty_copy( old_dset ) ;
/*-- Modify some structural properties.
    Note that the new_nvals just makes empty
    sub-bricks, without any data attached. --*/
EDIT_dset_items( new_dset ,
                 ADN_prefix
                            , output_prefix ,
                 ADN_directory_name, output_session ,
                 ADN_type
                                 , HEAD_FUNC_TYPE ,
                 ADN_func_type , FUNC_BUCK_TYPE,
                                                   /* no time! */
                 ADN_ntt
                                  , 0 ,
                 ADN_nvals
                                  , new_nvals ,
                 ADN_malloc_type , DATABLOCK_MEM_MALLOC ,
                ADN none ) :
if( THD_is_file(DSET_HEADNAME(new_dset)) ){
   fprintf(stderr,"*** Fatal error: file %s already exists!\n",
          DSET_HEADNAME(new_dset) );
  exit(1);
}
/*-- Loop over new sub-brick index,
    attach data array with EDIT_substitute_brick
    (this just attaches the pointer, it DOES NOT copy the array),
    then put some strings into the labels and keywords,
    and modify the sub-brick scaling factor
    (a zero scaling factor means don't scale the data array). --*/
```

```
*/
                       MRI_short , bar[iv] ) ; /* be sub-brick #iv.
                                            /* don't free bar[iv]! */
  EDIT_dset_items( new_dset ,
                    ADN_brick_label_one
                                               +iv, new_label[iv] ,
                    ADN_brick_keywords_replace_one+iv, new_keyw[iv]
                    ADN brick fac one
                                               +iv, new fac[iv]
                 ADN_none ) ;
}
/*-- Make sub-brick #2 be a t-test --*/
sax[0] = FUNC_TT_TYPE ;
sax[1] = 1.0;
sax[2] = degrees_of_freedom ;
EDIT_dset_items( new_dset ,
                 ADN_brick_stataux_one + 2 , sax ,
               ADN_none ) ;
/*-- write new dataset to disk --*/
DSET_write( new_dset ) ;
```

#### Adding Sub-Bricks to a Bucket Dataset

for( iv=0 ; iv < new\_nvals ; iv++ ){</pre>

In the above example, all the sub-bricks were created at once. They were initially empty, after the first call to EDIT\_dset\_items, but otherwise had all the structure needed. After a sub-brick has an actual data array attached to it, the ADN\_nvals code can no longer be used to change the number of sub-bricks in dataset.

If a dataset already has actual data attached to any of its sub-bricks, another method must be used to add a new sub-brick:

```
short * qbar ;
float    qfac ;
EDIT_add_brick( new_dset , MRI_short , qfac , qbar ) ;
```

will create a new sub-brick in the dataset, with data type short, scale factor qfac, and data array qbar. (The pointer qbar is just copied into the sub-brick—the data it points to now 'belongs' to the dataset and should not be freed by you!) If you wish to attach a label, keywords, or statistical parameters to this new brick, you would do this using EDIT\_dset\_items (using the correct index for the new sub-brick).

Note that if you are doing this to a 3D+time dataset, as opposed to a bucket dataset, then a little more needs to be done. See plug\_realtime.c for an example of how the *AFNI* real-time system uses EDIT\_add\_brick to grow a 3D+time dataset during image acquisition.

#### Accessing Sub-Brick Data

The following C macros can be used to access the contents of sub-bricks and their associated data. The argument ds is a pointer to a dataset struct, and the argument iv is a sub-brick index.

$\underline{\text{Macro}}$	Meaning
ISVALID_DSET(ds)	Returns 1 if ds is a valid pointer to a dataset, or 0 if it
	is not.
ISANATBUCKET(ds)	Returns 1 if ds is an anatomy bucket dataset, 0 if it is
	not.
ISFUNCBUCKET(ds)	Returns 1 if ds is a function bucket dataset, 0 if it is not.
ISBUCKET(ds)	Returns 1 if ds is a bucket dataset (function or anatomy), 0 if it is not.
DSET_BRICK_TYPE(ds,iv)	Returns an integer describing what type of data is stored in the sub-brick array.
DSET_BRICK_ARRAY(ds,iv)	Returns a pointer to the sub-brick array.
DSET_BRICK_FACTOR(ds,iv)	Returns the sub-brick floating point scale factor.
DSET_NVALS(ds)	Returns the number of sub-bricks in a dataset.
DSET_BRICK_LABEL(ds,iv)	Returns a pointer to the sub-brick label. This pointer will not be NULL. Do <i>not</i> write into this string!
DSET_BRICK_STATCODE(ds,iv)	Returns an integer with the statistical type of a subbrick. A positive value means that this sub-brick can be interpreted as a statistic. Note that if ds is on of the older 2-brick datasets such as fico, then calling this with iv=1 will return the correct code, even though that code is actually associated with the dataset as a whole, not the sub-brick.
DSET_BRICK_STATAUX(ds,iv)	Returns a pointer to a float array with the statistical parameters for this sub-brick. This may be NULL, which means that you did something wrong. Do not write into this array! The number of parameters in this array can be determined from the table in §1, or from FUNC_need_stat_aux[kv] where kv = DSET_BRICK_STATCODE(ds,iv).
DSET_BRICK_STATPAR(ds,iv,jj)	Returns the jj <sup>th</sup> statistical parameter for this sub-brick. This will be a float.

DSET\_BRICK\_KEYWORDS(ds,iv) Returns a pointer to the keywords string for this sub-

brick (char \*). Do not write into this string! This

pointer may be NULL.

DSET\_KEYWORDS(ds) Returns a pointer to the keywords string for the entire

dataset. Do not write into this string! This pointer may

be NULL.

#### Creating a Bucket from a 3D+time Dataset

I have written a utility routine to create a function bucket dataset from an input 3D+time dataset. This function takes as input a user-supplied function that returns the bucket values at each voxel. This function resides in 3dmaker.c (a new file), and can be called from a plugin or from a command-line program. Its calling sequence is:

The inputs to this function are:

old\_dset Pointer to old dataset;

note that this dataset must not be warp-on-demand.

new\_prefix String to use as filename prefix.

new\_datum Type of data to store in output brick;

if negative, will use datum from old\_dset.

ignore Number of data points to ignore at the start.

detrend If nonzero, this routine will detrend (a+b\*t)

each time series before passing it to user\_func.

nbrik Number of values (and sub-bricks) to create at each voxel location.

user\_func Function to compute outputs; discussed below.

user\_data Discussed below.

The output is a pointer to a new dataset. If NULL is returned, some error occurred.

The user\_func function should be declared like so:

The arguments to user\_func are:

npts	Number of points in ts array.
ts	One voxel time series array, ts[0]ts[npts-1]; note that this will always be a float array, and that ts will start with the ignore <sup>th</sup> point of the actual voxel time series.
ts_mean	Mean value of ts array.
ts_slope	Slope of ts array; this will be inversely proportional to tdelta (units of 1/sec); if detrend is nonzero, then the mean and slope will been removed from the ts array.
ud	The user_data pointer passed in here; this can contain whatever control information the user wants.
nbrik	Number of output values that this function should return for the voxel corresponding to input data ts.
val	Pointer to return values for this voxel; note that this is a float array of length nbrik, and that values you don't fill in will be set to zero.

Before the first timeseries is passed, user\_func will be called with arguments

```
(0.0, 0.0, nvox, NULL, 0.0, 0.0, user_data, nbrik, NULL)
```


where nvox = number of voxels that will be processed. This is to allow for some setup (e.g., malloc). After the last timeseries is passed, user\_func will be called again with arguments


```
(0.0, 0.0, 0, NULL, 0.0, 0.0, user_data, nbrik, NULL)
```

This is to allow for cleanup (e.g., free). Note that the only difference between these 'notification' calls is the third argument. After the new dataset is created, you will likely want to modify some of the auxiliary data associated with its sub-bricks (e.g., set statistical parameters and labels).

# 5 Changes in AFNI

If the active datasets are buckets, then the set of choosers in the Define Function control panel changes. The figure below shows the new bucket sub-brick choosers on the left; the old style sub-brick choosers are shown on the right for comparison (these are used with the non-bucket dataset types).





With bucket sub-brick choosers

With old-style choosers

Note that any sub-brick of a bucket dataset can be used as a threshold. This is true even if it does not have statistical parameters attached. (In that case, no *p*-value can be computed, of course.)

Two new buttons have been added to the Misc menu under the Define Datamode control panel: Anat Info and Func Info. These buttons will popup message windows with the output of program 3dinfo about the current anatomical and functional datasets. This is to help look up keywords and statistical types of sub-bricks. In addition, the FIM button has been removed from the Define Function control panel.

## 6 Still to Come

Things that are needed:

- Routines to deal with keyword lists, and a mechanism to allow the user to select subbricks (and datasets) based on keywords.
- A mechanism to allow the user to assemble datasets 'on-the-fly' using keyword and/or sub-brick index criteria. (A generalization of the syntax of 3dbucket is a possibility.)
- Applications that create buckets (e.g., multiple regression, ...).